

V2.0K Update Installation Instructions

Installation checklist

Use the following as a checklist of all necessary steps to follow when installing and configuring your new DigitizerPro software.

Step 1: Read through all necessary installation steps carefully before getting started.

Step 2: When the installation is complete, you will be prompted to restart your computer.

Step 3: Attach your security dongle only when prompted.

Step 4: This update, DigitizerPro/MB V2.0K, can only be installed as an update to an existing DigitizerPro/MB installation with a working DigitizerPro/MB dongle. If you do not have DigitizerPro already installed, you will need an upgrade kit with an upgrade dongle in order to upgrade a previous release of the Janome digitizing software such as Digitizer 10000.

Step 5: Chinese Traditional and Thai new languages Installation

Chinese Traditional and Thai languages are available from this version. These languages will not be installed with this update program. You need a full DigitizerPro/MB V2.0K installation to add Chinese Traditional and Thai languages or any additional languages you haven't installed previously.

Contact your Janome dealer to obtain a copy of DigitizerPro/MB V2.0K multi-language CD-ROM.

Step 6: Close all Windows programs but leave Windows running. Disable any virus scanning software you might be running in the background. Be aware of any messages from your firewall software (standard in Windows XP/Vista) requesting you to block access to any components of the installing software. DO NOT block any of the components.

Note: Most of your existing DigitizerPro/MB default settings will automatically be merged with the update installation. However, you will be required to re-select your machine model in both the MemoryCraft menu and the Options for Save As > JEF.

Installing DigitizerPro/MB V2.0K as an Update

Use the procedure outlined below to update DigitizerPro/MB software on your computer.

To install a DigitizerPro/MB Update

1 Download ALL five files - Disk1, data3, data4, data5 and data6 – and save them on your PC.



data3.cab



data4.cab



data5.cab



data6.cab



Disk1.exe

2 Double click 'Disk1.exe.' The file is unzipped and the folder named as "DigitizerML2UpdateTemp" is created automatically under C drive.

3 Copy the remaining four files - data3, data4, data5 and data6 – and paste them into My computer > C > **DigitizerML2UpdateTemp** which was created in the previous step.

4 Double click 'setup.exe' icon in **DigitizerML2UpdateTemp** folder to start installation.

5 A Welcome screen is displayed showing your current version and the version to which you are updating.

6 Click 'Next.'

7 Click 'Install.' Installation start automatically.

8 Click 'Finish' to restart your PC.

9 When your PC is restarted you are prompted to attach DigitizerPro dongle.

10. Attach DigitizerPro dongle on your PC to complete the update.